

# Installing Samba 2.0.6

---

ITOS Edition

\$Date: 2006/03/21 16:07:23 \$

---

Copyright 1999-2006, United States Government as represented by the Administrator of the National Aeronautics and Space Administration. No copyright is claimed in the United States under Title 17, U.S. Code.

This software and documentation are controlled exports and may only be released to U.S. Citizens and appropriate Permanent Residents in the United States. If you have any questions with respect to this constraint contact the GSFC center export administrator, <Thomas.R.Weisz@nasa.gov>.

This product contains software from the Integrated Test and Operations System (ITOS), a satellite ground data system developed at the Goddard Space Flight Center in Greenbelt MD. See <<http://itos.gsfc.nasa.gov/>> or e-mail <[itos@itos.gsfc.nasa.gov](mailto:itos@itos.gsfc.nasa.gov)> for additional information.

You may use this software for any purpose provided you agree to the following terms and conditions:

1. Redistributions of source code must retain the above copyright notice and this list of conditions.
2. Redistributions in binary form must reproduce the above copyright notice and this list of conditions in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgement:  
This product contains software from the Integrated Test and Operations System (ITOS), a satellite ground data system developed at the Goddard Space Flight Center in Greenbelt MD.

This software is provided 'as is' without any warranty of any kind, either express, implied, or statutory, including, but not limited to, any warranty that the software will conform to specification, any implied warranties of merchantability, fitness for a particular purpose, and freedom from infringement and any warranty that the documentation will conform to their program or will be error free.

In no event shall NASA be liable for any damages, including, but not limited to, direct, indirect, special or consequential damages, arising out of, resulting from, or in any way connected with this software, whether or not based upon warranty, contract, tort, or otherwise, whether or not injury was sustained by persons or property or otherwise, and whether or not loss was sustained from or arose out of the results of, or use of, their software or services provided hereunder.

## Installing and Configuring Samba 2.0.6

This describes how we install and configure Samba on ITOS computers. These instructions apply to development and well as operational systems running either Solaris or FreeBSD.

### Obtaining Samba

Get 'samba-2.0.6.tar.gz' from a trusted site, such as 'www.samba.org'.

### Installing Samba

In the following, \$DISTDIR is the directory containing the distribution tar files and \$WORKDIR is the directory where you're gonna build Samba.

You must run the 'make install' step, at least, as root.

```
# cd $WORKDIR
# tar xzpf $DISTDIR/samba-2.0.6.tar.gz
# cd samba-2.0.6/source
# ./configure --bindir=/usr/local/bin --localstatedir=/var/samba
#               --libdir=/etc/samba --mandir=/usr/local/man
#               --with-privatedir=/etc/samba/private
# make
# make install >install.log 2>&1
```

This puts all samba executables in /usr/local/bin and man pages in /usr/local/man. The configuration files go in /etc/samba, with the password file in /etc/samba/private/passwd. Transient and output files go in /var/samba.

As root, create /etc/samba/private, with mode 600. Add individual passwords with 'smbpasswd -a user', where 'user' is the user name for which you're adding the password. The program will prompt for the password just like the UNIX passwd program.

### Configuring Samba

The following is a sample configuration file. It is very simple, and doesn't include anything about printers, or home directories.

```
# This is the main Samba configuration file. You should read the
# smb.conf(5) manual page in order to understand the options listed
# here. Samba has a huge number of configurable options (perhaps too
# many!) most of which are not shown in this example
#
# Any line which starts with a ; (semi-colon) or a # (hash)
# is a comment and is ignored. In this example we will use a #
# for commentry and a ; for parts of the config file that you
# may wish to enable
#
# NOTE: Whenever you modify this file you should run the command "testparm"
```

```

# to check that you have not many any basic syntactic errors.
#
#===== Global Settings =====
[global]

    browseable = yes
    dead time = 30
    workgroup = itos_group
    server string = Samba Server
; Change the following to our network address, ending in a dot.
    hosts allow = 123.456.
    security = user
    encrypt passwords = yes
; Change this to our WINS server.
    wins server = wins.my.domain
    dns proxy = no
    follow symlinks = no
    wide links = no
    getwd cache = yes
    lm announce = yes
    local master = no
    map archive = no
    preserve case = yes
    syslog = 3
    debug level = 3

#===== Share Definitions =====

; A simple example:
; "somename" is the name of the share you want to make available.

[somename]
    comment = Tell here something about what the directory contains
; path to the actual directory you want to share.
    path = /export/somedir
; List UNIX groups beginning with "@", and individual user names.
    valid users = @us,you
; Change the following to "yes" to allow folks to write in the directory.
    writable = no
    create mask = 775

```

## Starting Samba

## Solaris 2.6/Solaris 7

To start Samba when a Solaris 2.6 or Solaris 7 computer boots you'll need one file with three names:

```
# cd /etc/init.d
/etc/init.d# cat > samba
#!/bin/sh
case "$1" in
'start')
    [ -x /usr/local/bin/smbd -a -f /etc/samba/smb.conf ] \
    && echo "starting smbd ..." \
    && /usr/local/bin/smbd
    ;;
'stop')
    [ -f /var/samba/locks/smbd.pid ] \
    && echo "kill smbd, pid 'cat /var/samba/locks/smbd.pid'" \
    && kill -TERM 'cat /var/samba/locks/smbd.pid'
    rm /var/samba/locks/smbd.pid
    ;;
'restart')
    [ -f /var/samba/locks/smbd.pid ] \
    && kill -HUP 'cat /var/samba/locks/smbd.pid'
*)
    echo "Usage: $0 [ start | stop | restart ]"
    ;;
esac
exit 0
^D
/etc/init.d# ln samba ../rc3.d/S95samba
/etc/init.d# ln samba ../rc3.d/K95samba
```